

FAQ_100216: System to calculate No. of Sampled Containers.

Path: Transaction Daily→RM/PM Store→Inward

PharmaSuite - [SOHAM PHARMACEUTICALS PVT. LTD., VATVA, 200910 - Material Inward]

Transactions Daily Master Parameter Reports Utility Exit Window

SOHAM **Material Inward** FmMatInw 2009-2010 24.02.2010

G. R. Details GP & Transport Details Inward Expenses

Location * VATVA Make * SOHAM Material Type * RM Series RM
 Inward Type * Purchase G.R.No RM090015 G.R. Date * 04-06-2009
 Vendor * DHAR001 DHARI CHEMICALS VADODARA
 Challan No 040609 Challan Date 04-06-2009 Material For

Mat.Code	Batch	Pack	Challan Qty	UOM	Purc. Ord. No *	Stock Qty	UOM	Inward No.
1SUGA02	010509	50X50	2500.0000	KG	PO00003	2500.0000	KG	DVDR090018

SUGAR (PHARMA GRADE) H Mfg. By DHANRAJ & CO. Material For

Material Status Testing Cenvat

Material Status Details

Challan Qty	2500.0000	KG	Gross Wt.		Condition of Goods		
+ Excess Qty		KG		Drums		Damage	NO
-Shortage Qty		KG	Mfg. Dt.	01-MAY-09		Seal	YES
= Actual Rec.	2500.0000	KG	Exp. Dt.	01-APR-14	Water Penetration	NO	
Stock Qty	2500.0000	KG	Retest Dt.	06-JUN-11	Label Condition	OK	
Container	50	DRUM	Reference Inward No		Outer Packing	OK	
					Inner Packing	OK	

Here it displays **50 drums** in “No. of Drums” and **18** in “No. of Sampled Container”

PharmaSuite - [SOHAM PHARMACEUTICALS PVT. LTD. , VATVA , 200910 - Material Issue For Testing]

Transactions Daily Master Parameter Reports Utility Exit Window

SOHAM Material Issue For Testing FmTstTran 2009-2010 24.02.2010

Location * VATVA Make * SOHAM Testing Issue Slip No VDMTR90008 **WIP**

Issue Type First Time Material Type * RM Issue Date * 05-06-2009

Send To * SELF001 SELF Q.C DEPARTMENT

City AHMEDABAD Sampled By B. N. PANDYA

Remarks

Code	Spec.	Mat.Inw.No.	No. of Sampled Container	Total Testing Qty.	Hold Qty.	UOM	Testing Charges
1SUGA02	IH	DVDR090018	18	0.0100		KG	0.00
1SUGA02	IH	DVDR090019	13	0.0100		KG	0.00

Material Name * SUGAR (PHARMA GRADE) **Delete**

Supplier DHARI CHEMICALS Mfg. Dt. MAY-2009

Challan No. 040609 Batch No. 010509 Exp. Dt. APR-2014

G.R. No. RM090015 Pack 50X50 ReTest Dt. 06-06-2011

No. of Drums 50 DRUM Stock Qty 2500.0000 KG A.R No. DVDR090018

Possible Reasons:

1. If the Material Type is **RM** and sub type is **ACTIVE** then 100% sampling is done.
2. And also when the sub-type is **INACTIVE** and Total no. of containers is ≤ 10 then 100% sampling is done.
3. And if the material is **Inactive**. and no. of containers is more than 10→
 In this case, No. of Sampled Container is calculated as follows:

$$= (\text{No of. Drums}-10)/5 + 10$$

$$= (50-10)/5 + 10$$

$$= 40/5+10$$

$$= 8+10$$

$$= \mathbf{18}$$